

Mail Server Settings


SMTP Outgoing Mail Server: smtp.teleguam.net
POP Incoming Mail Server: pop.teleguam.net

Step 1: Load Outlook Express

Step 2: Select Accounts from the Tools menu


Step 3: Click the Add Button

Step 4: Select Mail from the drop-down menu.




Step 5: Enter your name in the Display Name field.

Step 6: Click the Next button.



Step 7: Enter your Email Address. (Be sure you use your *username@teleguam.net*)

Step 8: Click the Next button.




The screenshot shows a Windows dialog box titled "Internet Connection Wizard" with a close button (X) in the top right corner. The main title of the dialog is "Internet E-mail Address". Below the title bar, there is a mouse cursor icon. The main content area contains the following text: "Your e-mail address is the address other people use to send e-mail messages to you." Below this, there are two radio button options. The first option is selected and is labeled "I already have an e-mail address that I'd like to use." Below this option is a text input field containing "username@teleguam.net" and a label "E-mail address:". Below the input field is the text "For example: someone@microsoft.com". The second option is labeled "I'd like to sign up for a new account from:" and has a dropdown menu showing "Hotmail". At the bottom of the dialog, there are three buttons: "< Back", "Next >", and "Cancel".

Step 9: Select POP3 from the drop down menu.

Step 10: Fill in the Incoming mail (POP3) server field with pop.teleguam.net

Step 11: Fill in the Outgoing mail (SMTP) server field with smtp.teleguam.net

Step 12: Click the Next button



The screenshot shows the 'Internet Connection Wizard' dialog box, specifically the 'E-mail Server Names' step. The window title is 'Internet Connection Wizard' and the subtitle is 'E-mail Server Names'. A mouse cursor is pointing at the 'Next >' button. The dialog contains the following text and input fields:

My incoming mail server is a server.

Incoming mail (POP3, IMAP or HTTP) server:


An SMTP server is the server that is used for your outgoing e-mail.
Outgoing mail (SMTP) server:

At the bottom, there are three buttons: '< Back', 'Next >', and 'Cancel'.

Step 13: In the Account name field, enter your Email Address.

Step 14: Enter your password into the Password field

Step 15: Click the Next button



The screenshot shows a Windows dialog box titled "Internet Connection Wizard" with a sub-header "Internet Mail Logon". The main text reads: "Type the account name and password your Internet service provider has given you." There are two input fields: "Account name:" containing "username@teleguam.net" and "Password:" containing "xxxxxxx". Below the password field is a checked checkbox labeled "Remember password". Further down, there is a paragraph: "If your Internet service provider requires you to use Secure Password Authentication (SPA) to access your mail account, select the 'Log On Using Secure Password Authentication (SPA)' check box." followed by an unchecked checkbox labeled "Log on using Secure Password Authentication (SPA)". At the bottom, there are three buttons: "< Back", "Next >", and "Cancel".

Step 16: Click the Finish button

